

DocAve® 6 Quickr Migrator

User Guide



Service Pack 10, Cumulative Update 1 Issued April 2018

Table of Contents

What's New in this Guide	4
About Quickr Migrator	5
Complementary Products	5
Submitting Documentation Feedback to AvePoint	7
Before You Begin	8
AvePoint's Testing Policy and Environment Support	8 8
Configurations	9
Agents	9
Required Permissions	10 11 13
Migration Speed Considerations	
Health Analyzer	15
Getting Started	16
Launching DocAve Quickr Migration	16
Navigating DocAve	17
About Online Migrations	19
Online Migration Overview	20
Pre-migration Configurations	21
Configuring Migration Databases	21
Configuring Quickr Connections	23
Configuring Filter Policies	24

Creating and Editing Filter Policies	25
Configuring Mapping Settings	26
User Mapping	26
Group Mapping	
Permission Mapping	26
Configuring Dynamic Rules	29
Managing Dynamic Rules	29
Creating and Editing Dynamic Rules	30
Setting Up a Quickr Migration Profile	31
Migration Options	31
Mapping Options	34
Advanced Options	37
Managing Sub-profiles	39
Editing an Existing Sub-profile	
Deleting an Existing Sub-profile	39
Downloading an Existing Sub-profile	39
Uploading a Configured Sub-profile	40
Performing a Quickr Migration	41
Select the Source and Destination Nodes	41
Creating Containers	43
Configuring the Run Now Interface	44
Configuring the Save As New Plan Interface	45
Configuring the Add Schedule Interface	
Quickr Migration for SharePoint Online	49
Supported and Unsupported Elements in Quickr Migrator	50
Managing Plans	54
Quickr Migrator Tool	55
Appendix A: Quickr Migration Database Information	56
Job Detail	56
Job Notification	61
Job Statistic	62
Job Logs	68

Appendix B: Quickr Migrator Customization Support Table	70
Appendix C: Quickr Migrator Configuration File	76
QuickrMigrationWorker.xml	76
Appendix D: Conflict Resolution	79
Container Level Conflict Resolution	79
Content Level Conflict Resolution	80
Notices and Copyright Information	8

What's New in this Guide

• General improvements for enhanced functionality.

About Quickr Migrator

DocAve Quickr Migrator provides an efficient and cost-effective solution for the transfer of places, rooms, folders, and pages from Quickr to Microsoft SharePoint 2010, SharePoint 2013, SharePoint 2016, and SharePoint Online. DocAve allows SharePoint administrators to easily automate the process of consolidating multiple Quickr content sources into SharePoint, therefore, maximizing return on investment in legacy content residing in Quickr.

Quickr Migrator allows organizations to:

- Streamline the data transfer easily from Quickr to SharePoint
- Preserve and map all associated metadata and security settings of Quickr content during the migration
- **Plan migration jobs according to business needs** with granular or bulk content migration and customizable job scheduling

To ensure a complete and successful Quickr migration, DocAve's Pre-Migration Scanner provides a detailed analysis of the migration before it is performed. The DocAve Pre-Migration Scanner will detect and notify you of any illegal characters, user permissions, user names, user domains, and other legacy elements that must be mapped in order to migrate successfully into SharePoint.

Organizations can further minimize business disruption and time-to-value by leveraging AvePoint Partner Services (APPS) to perform detailed data analysis, content and application migrations, and post-migration verifications.

As with all AvePoint software, our SharePoint Migration tools leverage only fully supported Microsoft methodologies and APIs.

Complementary Products

Many products and product suites on the DocAve 6 platform work in conjunction with one another. The following products are recommended for use with DocAve Quickr Migrator:

- DocAve Content Manager for SharePoint for restructuring or moving SharePoint content.
- DocAve Report Center for SharePoint to examine pain points in the SharePoint infrastructure and report on SharePoint user behavior and changes.
- DocAve Data Protection for setting backup and recovery points prior to adjusting SharePoint governance policies in this product.

•	DocAve Replicator to perform live or event-driven, as well as scheduled or offline replication. Synchronization and management of all content, configurations, and securities is performed with full fidelity.		

Submitting Documentation Feedback to AvePoint

AvePoint encourages customers to provide feedback regarding our product documentation. You can <u>Submit Your Feedback</u> on our website.

Before You Begin

Refer to the sections for system and farm requirements that must be in place prior to installing and using DocAve Quickr Migrator.

AvePoint's Testing Policy and Environment Support

Supported Software Environments

AvePoint is committed to testing against all major versions and service packs of SharePoint as well as the latest versions of Windows Server and SQL Server, as Microsoft announces support and compatibility.

*Note: AvePoint does not recommend or support installing DocAve on client operating systems.

Supported Hardware

AvePoint is committed to maintaining a hardware agnostic platform to ensure that DocAve operates on common Windows file sharing and virtualization platforms. To ensure that DocAve is hardware agnostic, AvePoint tests hardware that is intended to support SharePoint and DocAve infrastructure, storage targets, and hardware-based backup and recovery solutions, as supported by AvePoint's partnerships. AvePoint directly integrates with the following platforms: any Net Share, FTP, Amazon S3, AT&T Synaptic, Box, Caringo Storage, Cleversafe, DELL DX Storage, Dropbox, EMC Atmos, EMC Centera, Google Drive, HDS Hitachi Content Platform, IBM Spectrum Scale Object, IBM Storwize Family, Microsoft Azure Storage, NetApp Data ONTAP, NFS, OneDrive, Rackspace Cloud Files, and TSM.

All other hardware platforms that support UNC addressable storage devices are supported.

*Note: AvePoint has ended the test and development for Caringo Storage and DELL DX Storage in DocAve since DocAve 6 SP7 CU1, as the providers of these two platforms have stopped the platform maintenance.

*Note: Due to changes in the IBM Tivoli Storage Manager API, DocAve 6 Service Pack 6 and later versions require that TSM Client version 7.1.2 is installed on the Control Service and Media Service servers.

*Note: Most of the hardware partnerships referenced in this guide are intended to make use of advanced functionality (such as snapshot mirroring, BLOB snapshots, indexing, long-term storage, WORM storage, etc.), and are not indications that any changes to the product are required for basic support. In most cases, hardware can be supported with no change to the product.

Supported Backup and Recovery

DocAve supports BLOB backup storage according to the list of hardware platforms above. BLOB snapshot function, however, is currently only supported on OEM versions and NetApp hardware.

DocAve supports SQL content and Application database backups via the SharePoint Volume Shadow Copy Service (VSS) on all Windows and SQL server platforms listed above. DocAve also supports snapshot-based SharePoint VSS on all hardware listed above where the hardware partner has certified support with Microsoft.

DocAve supports application and configuration server backups for all the supported software environments listed above. DocAve 6 SP5 or later supports VM backup via Hyper-V/VMWare for the following operating systems: Windows Server 2008 R2, Windows Server 2012, Windows Server 2012 R2, and Microsoft Hyper-V Server 2012 R2.

Configurations

In order to use DocAve Quickr Migrator, the DocAve 6 platform must be installed and configured properly on your farm. DocAve Quickr Migrator will not function without DocAve 6 present on the farm.

To review a list of migration source versions and systems supported by DocAve Migrator, refer to Appendix C: Migration Source Environment in the <u>DocAve 6 Installation Guide</u>.

Agents

DocAve Agents are responsible for running DocAve jobs and interacting with the SharePoint object model. DocAve Agents enable DocAve Manager to communicate with the respective servers, allowing for DocAve Quickr Migrator commands to function properly.

*Note: The use of system resources on a server increases when the installed agent is performing actions. This may affect server performance; however, if the agent installed on a server is not being used, its system resource needs are very low.

For instructions on installing the DocAve Platform, DocAve Manager, and DocAve Agents, see the <u>DocAve 6 Installation Guide</u>.

Required Permissions

To install and use DocAve Quickr Migrator properly, ensure that the following permissions are met.

Required Permissions for the Source

Before using DocAve Quickr Migrator, ensure the DocAve Agent account in the source has the following permissions:

- Local System Permissions: If there are no strict limitations within your organization on the permissions that can be applied, add the source **DocAve Agent Account** to the local **Administrators** group. Otherwise, ensure the source Agent account has the following permissions:
 - Full Control permission to the Lotus Notes installation directory.
 - The permissions listed in <u>Local System Permissions</u>, which are automatically configured by DocAve during installation.
- 2. Quickr Permissions: The permissions must be manually configured prior to using DocAve 6 Quickr Migrator; it is not automatically configured.
 - Have the Manager role for all locations Quickr will be migrated.
- 3. SQL Permissions: These permissions must be manually configured prior to using DocAve 6 Quickr Migrator; they are not automatically configured.
 - Member has a Database Role of **db_owner** for Migration Database.
 - Member has a Server Role of **dbcreator** to SQL Server.

Required Permissions for the Destination: Migration to SharePoint On-Premises

Before using Quickr Migrator for SharePoint on-premises, ensure that the destination Agent account has the following permissions:

- Local System Permissions: The permissions are automatically configured by DocAve during installation. Refer to <u>Local System Permissions</u> for a list of the permissions automatically configured upon installation. If there are no strict limitations within your organization on the permissions that can be applied, you can simply add the **DocAve Agent Account** to the local **Administrators** group to apply all of the required permissions.
- 2. SharePoint Permissions: These permissions must be manually configured prior to using DocAve 6 Quickr Migrator; they are not automatically configured.
 - Member of the Farm Administrators group
 - Full Control to all zones of all Web applications via User Policy for Web applications
 - Managed Metadata Service Term Store Administrator
 - Other permissions required
 - Managed Metadata Service Full Control
 - Managed Metadata Service Administrator
- 3. SQL Permissions: These permissions must be manually configured prior to using DocAve 6 Quickr Migrator; they are not automatically configured.

- Member has a Database Role of db_owner for all of the databases related to SharePoint, including Content Databases, SharePoint Configuration Database, and Central Admin Database
- Member has a Database Role of db_owner for Migration Database
- Member has a Server Role of dbcreator to SQL Server

*Note: If forms based authentication (FBA) is selected as a Web application's claims authentication type, refer to <u>Forms Based Authentication Permissions</u> to configure additional settings for the Web application.

Required Permissions for the Destination: Migration to SharePoint Online

Before using Quickr Migrator for SharePoint Online, ensure that the following permissions are met:

Local System Permissions for DocAve Agent Account

For the registered SharePoint Online site collections/OneDrive for Business/Office group team sites, the DocAve Agent account is on the DocAve Agent machine that will run migration jobs. This machine must have a network connection or have configured Agent Proxy Settings. For more information about Agent Proxy Settings, refer to the DocAve 6 Control Panel Reference Guide.

For the registered SharePoint on-premises site collections, the DocAve Agent account is on the DocAve Agent machine that will run migration jobs. This machine must be the Central Administration server, one of the Web front-end servers of the farm where the registered site collections reside, or a machine that can communicate with the Central Administration server or one of the Web front-end servers.

The DocAve Agent account must have proper Local System permissions. These permissions are automatically configured by DocAve during installation. Refer to <u>Local System Permissions</u> for a list of the permissions automatically configured upon installation. If there are no strict limitations within your organization on the permissions that can be applied, you can simply add the **DocAve Agent Account** to the local **Administrators** group to apply all of the required permissions.

Required Permissions for the Account Used to Register Office 365 Objects

The required permissions for the Office 365 account that is used to register SharePoint Online site collections/OneDrive for Business/Office 365 group team sites via **Control Panel**, vary with registration methods and object types. Refer to the tables below for the details.

Method: Scan Office 365 Objects via Manual Object Registration/Dynamic Object Registration			
Object Type	Office 365 Account Role	Other Permissions	
SharePoint Online Site Collection	SharePoint Administrator	Managed Metadata Service: Term Store Administrator	
OneDrive for Business	Global Administrator		
Office 365 Group Team Site	SharePoint Administrator		

Method: Manually Add Office 365 Objects via Manual Object Registration > Manage Containers		
Object Type	Permissions	
SharePoint Online Site Collection	 A member of the Site Collection Administrator group. 	
OneDrive for Business Office 365 Group Team Site	 Managed Metadata Service – Term Store Administrator 	
Office 303 Group Team Site		

Required Permissions for the Account Used to Register SharePoint On-Premises Site Collections

The account that is used to register SharePoint on-premises site collections via **Control Panel** > **Manual Object Registration** > **Scan** must have the following permissions:

- Full Control permission to all zones of all Web applications via User Policy for Web Applications.
- Member has a Database Role of db_owner for all of the databases related to SharePoint, including Content Databases, SharePoint Configuration Database, and Central Admin Database.
- A member of the **Site Collection Administrator** group.
- Managed Metadata Service
 - o Term Store Administrator
 - Full Control
 - Administrator

The account that is used to manually add a single SharePoint on-premises site collection or import site collections in batch via **Control Panel** > **Manual Object Registration** > **Manage Objects** must have the following permissions to each site collection:

- A member of the **Site Collection Administrator** group.
- Managed Metadata Service
 - Term Store Administrator
 - o Full Control
 - Administrator

Local System Permissions

The following Local System Permissions are automatically configured during DocAve 6 installation:

- User is a member of the following local groups:
 - o IIS WPG (for IIS 6.0) or IIS IUSRS (for IIS 7.0)
 - Performance Monitor Users
 - DocAve Users (the group is created by DocAve automatically; it has the following permissions):
 - Full Control to the Registry of HKEY_LOCAL_MACHINE\SOFTWARE\AvePoint\DocAve6
 - Full Control to the Registry of HKEY_LOCAL_MACHINE\System\CurrentControlSet\Services\eventl og
 - Full Control to the Communication Certificate
 - Permission of Log on as a batch job (it can be found within Control Panel > Administrative Tools > Local Security Policy > Security Settings > Local Policies > User Rights Assignment)
 - Full Control to DocAve Agent installation directory

Forms Based Authentication Permissions

If forms based authentication (FBA) is selected as a Web application's claims authentication type, ensure at least one of the following conditions is in place:

 The Agent account must be a member with the Database Role of db_owner for the FBA database.

- Add the Agent account in the connectionStrings node in this Web application's web.config file to make the Agent account have permission to the FBA database.
 For details, refer to the instructions below:
 - Navigate to Start > Administrative Tools > Server Manager > Roles > Web Server (IIS) > Internet Information Services (IIS) Manager, find the desired Web application in the Sites list.
 - ii. Right-click the Web application and select **Explore**.
 - iii. A window pops up and you can find the web.config file in it.
 - iv. Open the web.config file with Notepad.
 - v. Find the **connectionStrings** node and specify a user that has access to the database that stores FBA security information.

Migration Speed Considerations

Speed is a very important factor when migrating content. To estimate how long your migration plans will take, in order to better inform stakeholder, the following key factors should be taken into consideration prior to running your migration plans.

- Network bandwidth between the Quickr and SharePoint environments
- SQL I/O and memory
- Memory on Web front-end servers
- Memory on the server hosting the DocAve Media service
- Number of CPUs on Web front-end servers
- Source environment deployment
 - Number of objects in source
 - Divide database and folder structures into small data sets before running the migration. Consider a granular migration approach.
 - o Size of objects in source
 - A single 1 GB file will migrate far quicker than a million files that have a sum of 1 GB.
 - Complexity of folders and sites
 - Prioritize content to be migrated into SharePoint, and utilize tools to establish co-existence throughout the course of the migration project to slowly roll-out SharePoint to users as their content becomes available.
 - o Whether DocAve has to create site collections during migration

- Use folders to break up large document libraries or data subsets to manage library size, consider utilizing filtering to migrate a subset of the data at a time.
- Whether securities are included in the plan (including mappings)
 - Permissions can be configured to be migrated in the migration plans.
- o Whether metadata is included in the plan

Health Analyzer

AvePoint recommends using Health Analyzer to check the prerequisites you need to correctly use DocAve Quickr Migration.

*Note: Only the users in the DocAve **Administrators** group can use Health Analyzer.

*Note: When creating Health Analyzer profiles, DocAve Quickr Migration recommends creating two different profiles to scan the source Agent and the destination Agent separately.

After selecting Quickr Migration as the module, all of the scan rules are selected by default, including the rules for the source environment and the rules for the destination environment. When the Health Analyzer job is finished, you can view the Health Analyzer results. If the scan rule is for the destination environment, but it is applied on the source environment, ignore the error or warning, and vice versa.

For more information about Health Analyzer, refer to the **DocAve 6 Installation Guide**.

Getting Started

Refer to the sections below for important information on getting started with DocAve Quickr Migration.

Launching DocAve Quickr Migration

To launch Quickr Migration and access its functionality, follow the instructions below:

- 1. Log into DocAve. If you are already in the software, click the **DocAve** tab. The **DocAve** tab displays all product suites on the left side of the window.
- 2. Click **Migration** to view all of the Migration modules.
- 3. Click Quickr Migration to launch that module.
 - *Note: If desired, access the **License Details** information for Migrator products from the **Migration** landing page.




Figure 1: DocAve Quickr Migration launch window.

Navigating DocAve

DocAve mimics the look and feel of many Windows products, making for an intuitive and familiar working environment. While there are many windows, pop-up displays, and messages within DocAve products, they share similar features and are navigated in the same ways.

Below is a sample window in DocAve. It features a familiar, dynamic ribbon, and a searchable, content list view.




Figure 2: Navigating DocAve.

- 1. Ribbon Tabs Allows users to navigate to the DocAve Welcome page and within the active DocAve modules.
- 2. Ribbon Panes Allows users to access the functionality of the active DocAve module.
- 3. Manage columns (●) Allows users to manage which columns are displayed in the list. Click the manage columns (●) button, and then select the checkboxes next to the column names in the drop-down list.
- 4. Hide the column (●) Allows users to hide the selected column.

- 5. Filter the column () Allows users to filter the information in the List View. Click the filter the column () button next to the column and then select the checkbox next to the column name.
- 6. Search Allows users to search the List View pane for a keyword or phrase. You can select **Search all pages** or **Search current page** to define the search scope.

*Note: The search function is not case sensitive.

7. Management Pane – Displays the actionable content of the DocAve module.

About Online Migrations

An Online Migration job migrates content, configurations, securities, and metadata from a source Quickr environment to a destination SharePoint environment when a network between the source and destination is available.

Online Migration Overview

To perform Online Migration jobs, the following steps must be performed in this order. Click the link to navigate to the corresponding section.

- 1. Pre-migration Configurations
 - Configuring Migration Databases
 - Configuring Quickr Connections
 - <u>Configuring Filter Policies</u> (Optional)
 - Configuring Mapping Settings (Optional)
 - Configuring Dynamic Rules (Optional)
- 2. Setting Up a Quickr Migration Profile
 - a. Migration Options
 - b. Mapping Options
 - c. Advanced Options
 - d. Managing Sub-profiles
- 3. Performing a Quickr Migration
 - a. Select the Source and Destination Nodes
 - Creating Containers
 - b. Select one of the following methods to perform an online migration
 - o Configuring the Run Now Interface
 - o Configuring the Save As New Plan Interface

Pre-migration Configurations

Configure the following settings before performing Quickr migration. Click the link to navigate to the corresponding section.

- Configuring Migration Databases
- Configuring Quickr Connections
- Configuring Filter Policies (Optional)
- Configuring Mapping Settings (Optional)
- <u>Configuring Dynamic Rules</u> (Optional)

Configuring Migration Databases

In order to use Quickr Migrator, you must configure a dedicated migration database to store links and detailed job information in SQL for every farm that will be using Quickr Migration. For detailed information on the Migration database schema, refer to <u>Appendix A: Quickr Migration Database Information</u>.

*Note: The version of SQL Server required to create a migration database must be SQL Server 2005 SP1 or higher.

- 1. On the **Home** tab, in the **Settings** group, click **Migration Database**. The **Migration Database** window appears.
- 2. Select the **farm** or **My Registered Sites** that will be using Quickr Migration. Each farm or My Registered Sites using Quickr Migration requires the following steps.
- 3. Click **Configure** in the **Manage** group. The **Configure** window appears.
- 4. Configure the following settings for the database that will store migration job data:
 - a. **Configure Migration Database** Enter a new **Database Server** and a **Database Name** for the migration database.
 - b. **Authentication** Select the authentication mode for the migration database.
 - Windows Authentication (recommended) Select this mode to verify the user's identity by Windows.
 - By default, the Specify a Window account checkbox is deselected and DocAve will create a new migration database or access the existing migration database using the destination DocAve Agent account.
 - To access the database server with a specified Windows account, select the Specify a Windows account checkbox and select a managed account profile from the Managed Account Profile

drop-down list or click **New Managed Account Profile** to create a new one in Control Panel. Then, click **Validation Test** to validate the account. For more information about creating managed account profile, refer to the <u>DocAve 6 Control Panel Reference</u> Guide.

 SQL authentication – Select this mode to verify the user's identity by SQL Server. Enter the user's account and password in the **Account** and **Password** fields. You can also validate the SQL database account by clicking **Validation Test**.

*Note: The specified account for creating or accessing the migration database must have a server role of **db_creator** for the SQL server where you want to create the migration database and have a database role of **db_owner** for the newly created/existing migration database.

c. **Failover Database Server** (optional) – Specify a failover database server. In the event that the migration database collapses, the data stored in the migration database will be transferred to this standby database.

Alternatively, you can configure a migration database in the **Advanced** settings by entering a connection string instead of configuring the settings in Step 4.

- a. Click **Advanced**; the **Connection String** section appears.
- b. Select the **Edit connection string directly** checkbox to activate this feature.
- c. Enter the connection string according to the example listed in the left pane.
 For more information about how to configure the connection string, refer to the ConnectionString property in SQL Server Books Online or SQL Server Tutorials by navigating to Start > Microsoft SQL Server > Documentation and Tutorials.
- d. Click Validation Test to test the connection.
- 5. Click **Save** to finish and save the configuration, or click **Cancel** to return to the **Migration Database** window without saving any configurations.

To view the configuration details of a migration database, select the migration database and click **View Details** on the ribbon in the **Migration Database** window. The detailed configurations are displayed in the **View Details** window.

Configuring Quickr Connections

To use Quickr Migrator, you must first configure the Quickr Migration connection so that the DocAve Agents can connect to the Quickr Servers. In the **Home** tab, click **Configure Connection** on the ribbon. The **Quickr Connection** window appears.

Managing Quickr Connections

The Quickr Connection interface displays any Quickr connections that you have previously created.

In this interface, you can change the number of Quickr connections displayed per page and the order in which they are displayed. To change the number of Quickr connections displayed per page, select the desired number from the **Show rows** drop-down menu in the lower right-hand corner. To sort the Quickr connections, click on a column heading such as **Name**, **Agent**, **Notes .INI File Path**, and **Last Modified Time**.

Perform the following actions in the **Quickr Connection** window:

- **Create** Click **Create** on the ribbon to create a new Quickr connection. For details, refer to <u>Creating and Editing Quickr Connections</u>.
- View Details Select a Quickr connection and click View Details on the ribbon.
 The configured settings for this Quickr connection are displayed in the View Details window. Here you can also click Edit on the ribbon to go to the Edit Quickr Connection window where you can make changes to this Quickr connection.
- Edit Select a Quickr connection and click Edit on the ribbon to change the configurations for this Quickr connections. For details, refer to <u>Creating and</u> <u>Editing Quickr Connections</u>.
- Delete Select one or more Quickr connections and click Delete on the ribbon.
 A confirmation window appears, confirming that you want to proceed with the deletion. Click OK to delete the selected Quickr connections, or click Cancel to return to the Quickr Connection window without deleting the selected Quickr connections.

Creating and Editing Quickr Connections

To create a new Quickr connection, click **Create** on the ribbon. To modify a Quickr connection, select the Quickr connection, and then click **Edit** on the ribbon.

In the **Create a New Quickr Connection** or **Edit the Quickr Connection** interface, configure the following settings.

- 1. **Name and Description** Enter a name for the Quickr connection. Then enter an optional description for this Quickr connection for future reference.
- 2. **Connection** Configure the following settings to connect the Quickr Server to the source DocAve Agent.
 - a. **Agent** Select a DocAve Agent installed in Quickr environment from the drop-down list.

- b. **NOTES.INI configuration file path** NOTES.INI file can be found in the Quickr server. The default path *C:\Program Files\lotus\notes.ini* is entered automatically. You can also enter the path by yourself, but make sure that the path you enter is the full path where NOTES.INI file is located.
- User ID file Click here link which is in the sentence below NOTES.INI
 configuration file path to load the user ID file, then select one from the dropdown list.
- d. **Password** Enter the password of the user that you have selected in User ID file.
- e. **Quickr Version** Select the version of your Quickr from the drop-down list. Click the **Validation Test** button to check the password.
- 3. Click **Save** to save the configurations and return to the **Quickr Connection** window, or click **Cancel** to return to the **Quickr Connection** window without saving any changes.

Configuring Filter Policies

Filter Policy allows you to set up filter rules so that you can control what pages within Quickr appear, and you can target content more precisely. By setting up and saving filter policies, you can apply the same filter policies to different Quickr migration plans without having to recreate them each time.

To access Filter Policy, click **Profile Settings** on the ribbon in the **Home** tab. On the **Profile Settings** page, click **Filter Policy** on the ribbon.

The **Filter Policy** window displays any filter policies that you have configured.

In this window, you can change the number of filter policies displayed per page and the order in which they are displayed. To change the number of filter policies displayed per page, select the desired number from the **Show rows** drop-down menu in the lower right-hand corner. To sort the filter policies, click on a column heading such as **Filter Policy Name**, and **Description**.

Perform the following actions in the **Filter Policy** window:

- **Create** Click **Create** on the ribbon to create a new filter policy. For details, refer to Creating and Editing Filter Policies.
- **View** Select a filter policy and click **View** on the ribbon to view detailed settings of a selected filter policy.
- **Edit** Select a filter policy and click **Edit** on the ribbon to change the configurations for this filter policy. For details, refer to <u>Creating and Editing Filter</u> Policies.
- Delete Select one or more filter policies and click Delete on the ribbon. A
 confirmation window appears, confirming that you want to proceed with the

deletion. Click **OK** to delete the selected filter policies, or click **Cancel** to return to the **Filter Policy** window without deleting the selected filter policies.

Creating and Editing Filter Policies

To create a new filter policy, click **Create** on the ribbon. To modify a filter policy, select the filter policy, and then click **Edit** on the ribbon.

In the **Create a New Filter Policy** or **Edit Filter Policy** window, configure the following settings:

- 1. **Name** Enter a **Name** for this filter policy.
- 2. **Description** Enter an optional **Description** for future reference.
- 3. **Filter Rule** A filter rule allows you to filter pages that you want to migrate by setting up a set of filter criteria. Follow the steps below to set up your own filter rules.
 - a. Click **Add a Filter Level Group** to create a **Time Range** filter level. The default rule is **Created Time** and you can select **Modified Time** from the drop-down list.
 - In the Condition column, time condition can be selected from Before, After, Within, and Older Than. Set up Time Zone and the exact time in the Value column.
 - c. Repeat the steps above to add multiple filter rules.
 - d. If you set multiple filter rules, you can change the logic option for these rules. By default, the logic is set to **And**. You can change the logic to **Or** by selecting it from the drop-down list.
 - And The data that meets all of the filter rules will be filtered to be included
 - Or The data that meets any one of the filter rules will be filtered to be included.
 - e. You can also change the order of these rules. Select a number from the **Order** drop-down list.
- 4. **Basic Filter Conditions** View the logical relationship of the filter rules in this area.
 - For example, if the logical relationship is ((1 And 2) Or 3), the data that meets both filter rule 1 and filter rule 2, or that meets the filter rule 3, will be included.
- 5. Click **Save** to save the configurations and return to the **Filter Policy** window, or click **Cancel** to return to the **Filter Policy** window without saving any changes.

Configuring Mapping Settings

Before performing a Quickr migration job, you may want to define User Mapping, Group Mapping, Permission Mapping, and Dynamic Mapping. Refer to the following sections to decide whether to configure the mapping settings, and learn how to configure the mapping settings.

User Mapping

User mapping maps an existing source node user to SharePoint user in the destination. During migration, Migrator will replace the source username with your specified username in the destination.

To access User Mapping, click **Profile Settings** on the ribbon in the **Home** tab. Then in the **Profile Settings** interface, click **Mappings** and select **User Mapping** on the ribbon. The **Control Panel** appears.

For detailed instructions on setting up user mapping, refer to the <u>DocAve 6 Control Panel</u> <u>Reference Guide</u>. Make sure that the source username that you input in the column of **Source Username** is in the following format:

- username/orgname
- username/orgname/orgname
- username/orgname/orgname/

The organization in Quickr can be multilevel and here the orgname you enter can also be multilevel.

Group Mapping

Use group mapping to map an existing source group name to a SharePoint group. During the migration, Migrator will replace the source group name with your specified group name in the destination node.

To access Group Mapping, click **Profile Settings** on the ribbon in the **Home** tab. Then in the **Profile Settings** interface, click **Mappings** and select **Group Mapping** on the ribbon. The **Control Panel** appears.

For detailed instruction on setting up group mapping, refer to the <u>DocAve 6 Control Panel</u> <u>Reference Guide</u>.

Permission Mapping

Quickr Migration migrates permissions of Quickr places, rooms, and folders. Permission mapping allows you to map permissions in the source to SharePoint permissions in the destination. During the migration, Migrator will replace the source permission with SharePoint

permission levels of Default Permission Mapping or your specified permission levels in the destination node.

*Note: If a user mapping and a permission mapping are used simultaneously, the permission of the destination user is the merged result of the mapped user's permission and the mapped permission.

Managing Permission Mappings

To access Permission Mapping, click **Profile Settings** on the ribbon in the **Home** tab. Then in the **Profile Settings** interface, click **Mappings** and select **Permission Mapping** on the ribbon. In the **Permission Mapping** window, all permission mappings that you have created are displayed.

In this window, you can change the number of permission mappings displayed per page and the order in which they are displayed. To change the number of permission mappings displayed per page, select the desired number from the **Show rows** drop-down list in the lower right-hand corner. To sort the permission mappings, click on a column heading such as **Name** and **Description**.

Perform one of the following actions on a selected permission mapping:

- **Create** Click **Create** on the ribbon to create a new Permission Mapping. For details, refer to Configuring and Editing Permission Mappings.
- View Details Select a permission mapping and click View Details on the ribbon. The configured settings for this permission mapping are displayed in the View Details window. Here you can also click Edit on the ribbon to go to the Edit window where you can make changes to this permission mapping.
- **Edit** Select a permission mapping and click **Edit** on the ribbon to change the configuration of this permission mapping. For details, refer to <u>Configuring and Editing Permission Mappings</u>.
- Delete Select one or more permission mappings and click Delete on the ribbon. A confirmation window appears, confirming that you want to proceed with the deletion. Click OK to delete the selected permission mappings, or click Cancel to return to the Permission Mapping window without deleting the selected permission mappings.

Configuring and Editing Permission Mappings

To create a new permission mapping, click **Create** on the ribbon. To edit a permission mapping, select the permission mapping and then click **Edit** on the ribbon.

In the **Create** or **Edit** window, configure the following settings:

- 1. **Name and Description** Enter a name for the permission mapping that you are about to create or edit. Then enter an optional **Description**.
- 2. Permission Mapping Set up the mapping of Quickr permissions to SharePoint permissions. Choose a SharePoint permission level from the SharePoint Permission Level drop-down list. We do not recommend changing the default permission mapping. If there is no SharePoint permission level that meets your requirements, you can customize one by selecting New SharePoint Permission Level from the drop-down list. For details on creating a new SharePoint permission level, refer to Creating and Editing SharePoint Permission Levels.

SharePoint Permission Levels

You can manage SharePoint permission levels by creating a new permission level, viewing details of a level, editing a level, or deleting a level.

To access Manage SharePoint Permission Level, click **Profile Settings** on the ribbon on the **Home** tab. Then in the **Profile Settings** interface, click **Mappings** and select **Permission Mapping** on the ribbon. In the **Permission Mapping** interface, click **Manage SharePoint Permission Level** on the ribbon.

The **Manage SharePoint Permission Level** window displays all permission levels that you have created.

In this window, you can change the number of SharePoint permission levels displayed per page and the order in which they are displayed. To change the number of SharePoint permission levels displayed per page, select the desired number from the **Show rows** drop-down list in the lower right-hand corner. To sort the SharePoint permission levels, click on a column heading such as **Name** and **Description**.

Perform the following actions in the **Manage SharePoint Permission Level** page.

- **Create** Click **Create** on the ribbon to create a new SharePoint permission level. For details, refer to <u>Creating and Editing SharePoint Permission Levels</u>.
- View Details Select a SharePoint permission level and click View Details on the ribbon. The configured settings of a customized permission level or the default settings of a default SharePoint permission level are displayed in the View Details window.
- **Edit** Select a SharePoint permission level and click **Edit** on the ribbon to change the configurations for this SharePoint permission level. For details, refer to Creating and Editing SharePoint Permission Levels.

*Note: Default SharePoint permission levels are displayed as default, including Contribute, Design, Edit, Full Control, Read, and View Only. They are not editable.

Delete – Select one or more SharePoint permission levels and click Delete on the ribbon. A confirmation window appears, confirming that you want to proceed with the deletion. Click OK to delete the selected permission levels, or click Cancel to return to the Manage SharePoint Permission Level window without deleting the selected permission levels.

Creating and Editing SharePoint Permission Levels

To create a new SharePoint permission level, click **Create** on the ribbon. To modify a customized SharePoint permission level, select the permission level, and then click **Edit** on the ribbon.

In the **Create a New SharePoint Permission Level** or **Edit the SharePoint Permission Level** window, configure the following settings:

- 1. **Name and Description** Enter a **Name** for this permission level that you are about to create or edit. Then enter an optional **Description** for future references.
- Permissions Choose which permissions to include in this permission level. You can select specified permissions of List Permissions, Site Permissions, and Personal Permissions by selecting the checkbox before a specified permission. Select the Select All checkbox to select or clear all permissions.
- 3. Click **Save** to save the configuration and return to the **Manage SharePoint Permission Level** window, or click **Cancel** to return to the **Manage SharePoint Permission Level** window without saving any change.

Configuring Dynamic Rules

Dynamic rule maps the Quickr field names and the corresponding values to SharePoint column names and column values using the DLL files customized in C#.

Managing Dynamic Rules

To access Dynamic Mapping, click **Profile Settings** on the ribbon of **Home** tab. In the **Profile Settings** tab, click **Dynamic Rule** on the ribbon. The **Dynamic Rule** interface appears.

In the **Dynamic Rule** window, you will see a list of previously configured dynamic rules.

In this window, you can change the number of dynamic rules displayed per page and the order in which they are displayed. To change the number of dynamic rules displayed per page, select the desired number from the **Show rows** drop-down menu in the lower right-hand corner. To sort the dynamic rules, click on a column heading such as **Name**, **Description**, **DLL File Name**, and **Last Modified Time**.

You may perform the following actions to a Dynamic Rule:

• **Create** – Click **Create** on the ribbon to create a dynamic rule. For details, refer to <u>Creating and Editing Dynamic Rules</u>.

- View Details Select a dynamic rule and click View Details on the ribbon. The
 configured settings for this dynamic rule are displayed in the View Details
 window. Here you can also click Edit on the ribbon to go to the Edit the
 Dynamic Rule window where you can make changes to this dynamic rule.
- Edit Select a dynamic rule and click Edit on the ribbon to change the
 configuration of this dynamic rule. For details, refer to <u>Creating and Editing</u>
 Dynamic Rules.
- Delete Select one or more dynamic rules and click Delete on the ribbon. A
 confirmation window appears, confirming that you want to proceed with the
 deletion. Click OK to delete the selected dynamic rule, or click Cancel to return to
 the Dynamic Rule window without deleting the selected dynamic rules.

Creating and Editing Dynamic Rules

To create a new dynamic rule, click **Create** on the ribbon. To edit a dynamic rule, select the dynamic rule and then click **Edit** on the ribbon.

In the **Create a New Dynamic Rule** window or **Edit the Dynamic Rule** window, configure the following settings:

- 1. **Name and Description** Enter a **Name** for the dynamic rule that you are about to create or edit. Then enter an optional **Description**.
- Upload a DLL File Browse a dynamic rule of DLL file customized in C# from the local path. A DLL file enables you to configure your own mappings. Click Browse, and then navigate to the DLL file you want to use. Select the specified DLL file and then click Open.
 - *Note: AvePoint provides a sample code for the DLL file. Click the **Download the Sample Code** link in the left description to download the sample code.
- Click Save to save the configuration and return to the Dynamic Rule window. Click Cancel to return to the Dynamic Rule window without saving any configuration or changes.

Setting Up a Quickr Migration Profile

The migration profile allows you to define numerous settings for the migration jobs, including Migration Options, Filter Options, Mapping Options, and Advanced Options.

While it is theoretically possible to run an online migration job using the default migration profile without configuring the settings described in the sections below, it is **strongly** recommended that you configure these settings in order to ensure appropriate content management during migration.

Follow the instructions below to create a migration profile.

- 1. On the **Home** tab, click **Profile Settings** in the **Profile** group. The **Profile Settings** tab appears.
- 2. In the **Profile/Sub-profile** group, click **New**.
- 3. Enter a profile name in the pop-up window and click **Save**.
- 4. Select the **Migration Options** from the left-hand pane. Select a Migration Options subprofile from the drop-down list. For details about this section, refer to <u>Migration Options</u>.
- 5. Select the **Filter Options** from the left-hand pane. Select a filter policy from the dropdown list or click **New Filter Policy** from the drop-down list to create a new filter policy. For details on creating a filter policy, refer to <u>Creating and Editing Filter Policies</u>.
- 6. Select the **Mapping Options** from the left-hand pane. Select a Mapping Options subprofile from the drop-down list. For details about this section, refer to <u>Mapping Options</u>.
- 7. Select the **Advanced Options** from the left hand pane. Configure the **Dynamic Rule**, the **Character Length Settings**, and the **Illegal Character Replacement Settings**. For details about this section, refer to **Advanced Options**.
- 8. Click **Save** to save the profile. Alternatively, click **Save As** and enter a profile name to save it as another profile. Select **Save and replace the existing main profile** to replace the original profile. Otherwise, it is saved without removing the original profile. Click **Discard Changes** to clear all the modifications having been made to the current main profile.

Migration Options

Migration Options allow you to configure which content settings and security settings can be migrated. Set up a Migration Options sub-profile by the following steps.

- 1. On the **Home** tab, click **Profile Settings** in the **Profile** group. The **Profile Settings** tab appears.
- 2. Click **Migration Options** on the left-hand pane.

- 3. In the **Sub-profile** group, click **Edit Sub-profile** to make the **Migration Options** field active.
- 4. In the **Profile/Sub-profile** group, click **New**.
- 5. Enter a sub-profile name in the pop-up window and click **Save**.
- 6. Click the **Content** tab to configure the following content migration settings:
 - **Managed Path** When choosing a Web application, site collection, or site as the destination node, a site collection, site, and/or child site will be created automatically during the migration job. You can define the managed path, the site template, and the site language for the created site collection/site/child site.
 - Customize a managed path Enter a customized managed path in the text box. Sites is provided as default.
 - *Note: This feature only takes effect when a SharePoint on-premises Web application is selected as the destination node.
 - Site template Select a site template from the drop-down list. By default,
 Team Site is selected.
 - Site language Select a site language from the drop-down list. English is selected by default.
 - *Note: If the selected site language does not exist in the destination, the site collection or site cannot be created successfully, and the source place and room cannot be migrated to the destination.
 - **Navigation Options** Choose navigation design options for destination sites that are generated from a Quickr place or room.
 - Display the site on the top link bar of the parent site when creating a site
 - Display the site on the Quick Launch of the parent site when creating
 - o Inherit top link bar of the parent site when creating a site
 - **Root Page Option** Enter the name of the library or list that the source root pages are migrated to. **Root** is provided as the default name.
 - *Note: The library or list template is determined by what you select in **Default** List **Template**.
 - Image Options Normally the embedded images in the source Quickr pages are
 added as attachments of items, which are generated from the pages. To extract
 the embedded images from the items and collect them in a picture library in
 SharePoint, select the Extract embedded images from Quickr into Picture
 Library checkbox. Quickr Picture Library is provided as the default name of the

- picture library where you wish the embedded images to be migrated. You can also customize the name by entering a picture library name in the text box.
- Attachment Migration Options Allows you to collect the attachments that are
 normally migrated as attachments of the items generated from Quickr pages to a
 separated document library in SharePoint. Select the Migrate attachments to
 separated Document Library checkbox. Quickr Attachment Library is provided
 as the default name of the document library where you wish the attachments to
 be migrated. You can also customize the name by entering a document library
 name in the text box.
- **Folder Structure Management** Choose whether to collapse the folder structure of the migrated content.
 - Collapse all the folder structure Migrates all of the pages of the
 nested folders to a same library or list by breaking the source folder
 structure. Select the Add a column to keep the source path checkbox to
 keep the source path of pages and enter the column name in the text box.
 By default, DocAve Source Path is provided.
 - ***Note**: If you migrate more than 2000 items at one time to a destination, SharePoint performance might be affected.
 - ***Note**: If you have configured a list mapping for the source top-level folder, the library or list template is determined by the list mapping. If no list mapping is configured for the source top-level folder, the library or list template is determined by what you selected in **Default List Template**.
- Index Migration Options Choose whether to migrate the source index to a Links list in the destination. Select the Migrate the source index to a Links list checkbox and enter a list name in the text box. By default, Index is provided.
- **Default List Template** Select a default list template from the drop-down list. This list template will be used as the template of the lists that are generated from the source top-level folders.
- 7. Click the **Security** tab to configure **Permission Inheritance**, which allows you to choose whether the site generated from the source place or room will inherit its parent site permission.
- 8. Click **Save** to save the sub-profile. Alternatively, click **Save As** and enter a sub-profile name to save it as another sub-profile. Select **Save and replace the existing sub-profile** to replace the original sub-profile. Otherwise, the sub-profile is saved without removing the original sub-profile. Click **Discard Changes** to clear all modifications having been made to the current sub-profile.

Mapping Options

Mapping Options allow you to configure list mapping, content type mapping, and security mapping. Set up a Mapping Options sub-profile by the following steps.

- 1. On the **Home** tab, click **Profile Settings** in the **Profile** group. The **Profile Settings** tab appears.
- 2. Click **Mapping Options** on the left-hand pane.
- 3. In the **Sub-profile** group, click **Edit Sub-profile** to make the **Mapping Options** field active.
- 4. In the **Profile/Sub-profile** group, click **New**.
- 5. Enter a sub-profile name in the pop-up window and click **Save**.
- 6. Click the **List Mapping** tab and configure the following settings to map Quickr folders to SharePoint lists. A default list mapping is provided to map the source **Library** folder to the destination **Library** with the template of Document Library.
 - a. Click **Add a List Mapping** and then a mapping entry appears for you to configure relevant rules.
 - b. In the text box under the **Quickr Place/Room Name** column, enter the name of the Quickr place or room where the Quickr folder you wish to map resides.
 - *Note: You can leave the **Quickr Place/Room Name** as blank. The list mapping will take effect on all folders that have the same folder name within the selected source nodes.
 - c. In the text box under the **Quickr Folder Name** column, enter the name of the Quickr folder that you wish to map.
 - d. In the text box under the **SharePoint List Name** column, enter the name of the SharePoint list that you wish the Quickr folder to be mapped to. If the entered list name does not exist in the destination, a new list with the entered name will be created automatically during the migration. If you enter an existing list, make sure the list template you select in **step e** is the same as that of the existing one; otherwise, a new list with the selected list template will be created in the destination during the migration and a suffix (_1) is added at the end of the list name.
 - e. Select or enter a template for your specified SharePoint list from the **SharePoint List Template** drop-down list. Custom List, Document Library, Wiki Page Library, and Discussion Board are provided.
 - *Note: Discussion Board is only supported when the language of the destination site collection is English.
 - f. Repeat the steps above to add more mappings.

- g. To delete one or more list mappings, select them and then click **Delete the Selected List Mapping(s)**. You can also click the delete (X) button to remove a list mapping.
- *Note: The source folder Calendar, Tasks, Index, and Root are not supported for List Mapping.
- 7. Configure the **Content Type Mapping**. You can choose to configure content type and column mapping. Click **Content Type Mapping** on the tab to use the content type mapping that is created by the Migrator Tool or to configure it manually.
 - Choose Use the content type mapping generated by Migrator Tool to automatically apply the content type mapping that you configured in the DocAve Migrator Tool during the migration.
 - *Note: If you choose this option, make sure that you have generated the content type mapping by the DocAve Migrator Tool; otherwise, the metadata of the source pages will not be migrated to the destination.
 - To configure the content type mapping in this page, select the Manually configure the content type mapping option and the Rule tab appears.
 Configure the following settings to set up a rule:
 - Content Type Mapping This is used to map a Quickr form to a SharePoint content type. Enter the name of a Quickr form in the Quickr Form column, and enter the name of a SharePoint content type in the SharePoint Content Type column.

Note the following:

- If the SharePoint content type does not exist in the destination, a new content type with the entered name will be created automatically during the migration.
- If you enter an existing content type in SharePoint, by default, the content type will be updated. If you do not wish to update this content type, you need to disable Update Content Type in a configuration file. On the destination DocAve Agent server, navigate to
 - ...\AvePoint\DocAve6\Agent\data\Migrator\QuickrSettings\Configur ationFile to open QuickrMigrationWorker.xml with Notepad and change the value of <ContentTypeConfig
 UpdateContentType="True"> to False.
- Column Mapping Allows you to specify the SharePoint column name and SharePoint column type for the mapped Quickr field. Click Add a Column Mapping. Enter the name of a Quickr field in the Quickr Field Name column, and enter the name of a SharePoint column in the

SharePoint Column Name column. Then select a SharePoint column type for this column from the **SharePoint Column Type** drop-down list.

Repeat the steps by clicking **Add a Column Mapping** to add more column mappings. To delete one or more column mappings, select the mappings and then click **Delete the Selected Column Mapping(s)**. You can also click the delete (X) button to remove a column mapping.

*Note: If you select Managed Metadata, it requires you to specify the term set path, and choose whether to allow multiple values in this column. For example, in the Term Set Path text box, System is the group name; ";" is the separator; Keywords stands for the term set. Select the Allow multiple values checkbox to define multiple values for the column. You can customize which separator will be used to separate multiple values in the text box. ";" is provided as default.

Click the plus (*) button beside the **Rule 1** tab to add more rules.

- 8. Click the **Security Mapping** tab to choose user mapping, group mapping, permission mapping, and configure AD group mapping.
 - **User Mapping** Select a user mapping from the drop-down list or click **New User Mapping** in the drop-down list to create a new one. For details on creating a user mapping, refer to the <u>DocAve 6 Control Panel Reference Guide</u>.
 - Group Mapping Select a group mapping from the drop-down list or click New Group Mapping in the drop-down list to map a source group to a SharePoint group. For details on creating a group mapping, refer to the <u>DocAve 6 Control</u> Panel Reference Guide.
 - AD Group Mapping Allows you to map the Quickr group to a specified AD group which exists in the domain of the SharePoint environment. Click Add an AD Group Mapping, then enter the name of the Quickr group in the column of Quickr Group Name and the name of the AD group in the column of AD Group Name. Repeat the steps by clicking AD Group Mapping to add more AD Group Mappings. To delete a one or more AD group mappings, select the mappings and then click Delete the Selected AD Group Mapping. You can also click the delete (X) button to remove an AD group mapping.
 - **Permission Mapping** Select a permission mapping from the drop-down list or click **New Permission Mapping** to create a new one. For details on creating a permission mapping, refer to Configuring and Editing Permission Mappings.
 - ***Note**: If you do not configure or select any permission mapping, the default permission mapping will be applied during the migration.
- 9. Click **Save** to save the sub-profile. Alternatively, click **Save As** and enter a sub-profile name to save it as another sub-profile. Select **Save and replace the existing sub-**

profile to replace the original sub-profile. Otherwise, the new sub-profile is saved without removing the original sub-profile. Click **Discard Changes** to clear all modifications having been made to the current sub-profile.

Advanced Options

Advanced Options allow you to configure Dynamic Rule, Character Length Settings and Illegal Character Replacement Settings. To set up Advanced Options, complete the following steps:

- 1. On the **Home** tab, click **Profile Settings** in the **Profile** group. The **Profile Settings** tab appears.
- 2. Click **Advanced Options** on the left-hand pane. You can configure the following settings:
 - Dynamic Rule Maps the source Quickr field names and the corresponding values to SharePoint column names and column values. Select a dynamic rule from the drop-down list or click New Dynamic Rule to create a new one. For details on creating a dynamic rule, refer to Creating and Editing Dynamic Rules.
 - **Character Length Settings** This is used to set character length limitations for folder name, file name, and SharePoint URL.
 - Maximum Length of the folder name The default value is 60 and you can define the value between 1 and 260. Note that only the SharePoint 2016 or SharePoint Online folder name length can be between 129 and 260 characters.
 - If the folder name exceeds the limitation, the extra characters will be pruned from the end. For example, a folder migrated from a database is named **abcdef** in the source and the value that you set here is 5. The folder will be named **abcde** after the migration.
 - Maximum Length of the file name The default value is 80 and you can define the value between 1 and 260. Note that only the SharePoint 2016 or SharePoint Online file name length can be between 129 and 260 characters.
 - If the file name, including the file extension, exceeds the limitation, the extra characters will be pruned from the end. For example, a file is named **abcdef.txt** in the source and the value that you set here is 5. The file will be named **a.txt** after the migration.
 - Maximum Length of the SharePoint URL The default value is 255. The length of a SharePoint on-premises object URL must be between 1 and 260 characters. The length of a SharePoint Online object URL must be between 1 and 400 characters. The length of the SharePoint URL is

calculated from the first character of the managed path after /. When the folder or file's URL exceeds the limit, the migration results are as follows:

- If the folder URL exceeds the limit, the folder and its content will be migrated to its previous level folder until the folder URL does not exceed the limit. If there is a file whose URL exceeds the limit within a folder, it will be migrated to its previous level folder until the file URL does not exceed the limit.
- If the file URL exceeds the limit, the file will be migrated to its previous level folder until the file URL do not exceeds the limit.
- Illegal Character Replacement Settings This is used to replace illegal SharePoint characters with valid characters. You can modify and add the illegal character mappings for group level, folder level, and file level to the specified characters in SharePoint. By default, all illegal characters are replaced with an underscore (_). Click the Group Level, Folder Level, or File Level tab.
 - To modify an illegal character mapping, double-click an underscore in the Replace with column behind an illegal character and change it to a new character.
 - To add an illegal character mapping, click Add an Illegal Character. Then, enter the illegal character in the Illegal character in SharePoint column and enter the corresponding valid character in the Replace with column. Click Add an Illegal Character again and another illegal character mapping can be created.
 - To delete one or more illegal character mappings, select the mappings and click **Delete the Selected Illegal Character(s)**. You can also remove an illegal character mapping by clicking the delete (X) button.

Note the following:

- In SharePoint 2016, ~, &, {, and } are not folder level illegal characters; ~, &, *, :, {, }, and | are not file level illegal characters any more. You can delete mappings of these characters, but note that the deletion may result in errors on migration jobs if the profile is applied to jobs whose destination is SharePoint 2010, SharePoint 2013, or SharePoint Online.
- In SharePoint Online, # and % are not folder level and file level illegal characters any more. You can delete mappings of these characters, but note that the deletion may result in errors on migration jobs if the profile is applied to jobs whose destination is SharePoint on-premises.
- If you want to delete mappings for default illegal characters, you must disable the <IsEnableIllegalCharReplacement

Flag="true"/> node in the

MigrationCommonConfiguration.xml configuration file. The file is located in the

- ...\AvePoint\DocAve6\Agent\data\Migrator\MigrationCommonMigr ator directory on the destination DocAve Agent server. Otherwise, the deleted default illegal character will still be replaced with an underscore ().
- *Note: If the name of a migrated folder ends with one or more periods (.), Quickr Migration will remove all periods (.) during the migration job. If the name of a migrated file ends with one or more periods (.), Quickr Migration will replace the last period (.) with an underscore (_) during the migration job.

Managing Sub-profiles

Refer the information below to manage an existing sub-profile.

Editing an Existing Sub-profile

To edit an existing sub-profile, complete the following steps:

- 1. Select an existing sub-profile from the **Sub-Profile** drop-down list.
- 2. Click **Edit Sub-profile** in the **Sub-profile** group.
- Click Save in the Profile/Sub-profile group to save the sub-profile settings.
 Alternatively, click Save As and enter a sub-profile name to save it as another sub-profile. Select Save and replace the existing sub-profile to replace the original sub-profile.

Deleting an Existing Sub-profile

To delete an existing sub-profile, complete the following steps:

- 1. Select an existing sub-profile from the **Sub-Profile** drop-down list.
- 2. Click **Delete** in the **Profile/Sub-profile** group to delete the sub-profile, or click **Delete** next to the sub-profile name in the drop-down list.
 - ***Note**: The default sub-profile and the sub-profile used in the main profile cannot be deleted.

Downloading an Existing Sub-profile

To download an existing sub-profile, complete the following steps:

 In the Profile Settings tab, click Migration Options or Mapping Options on the lefthand panel.

- 2. Click **Edit Sub-profile** in the **Sub-profile** group to make the **Migration Options** or **Mapping Options** field active.
- 3. Click **Download** in the **Sub-profile** group to save the sub-profile to the local disk.

Uploading a Configured Sub-profile

To upload a configured sub-profile, complete the following steps:

- 1. In the **Profile Settings** interface, click **Migration Options** or **Mapping Options** on the left panel.
- Click Edit Sub-profile in the Sub-profile group to make the Migration Options or Mapping Options field active.
- 3. Click **Upload** in the **Sub-profile** group.
- 4. Select a configured sub-profile and click **Open** to upload it. If a sub-profile having the same name exists in DocAve, you have two options:
 - **Upload as a new profile** Uploads the sub-profile and adds a suffix in the sub-profile name, for example, **subprofile_1**.
 - Overwrite current profile Replaces the existing sub-profile. The Default
 Mappings and Default Migration Options sub-profiles cannot be overwritten.

Performing a Quickr Migration

A Quickr Migration migrates contents, securities, and configurations from Quickr to the SharePoint environment.

To start a Quickr migration job, click **Online Migration** on the ribbon.

To perform a Quickr migration job, follow the instructions below.

Select the Source and Destination Nodes

- 1. Click **Select Source** in the **Source** pane or in the **Actions** group on the ribbon to select the source. The **Select Source** window appears. Configure the following settings.
 - a. Agent Select the DocAve Agent installed in Quickr environment from the dropdown list.
 - b. **Connection** Select the Quickr connection.
 - c. **Quickr Server** Select the source Quickr server from the drop-down list.
 - d. Click **OK** to complete configuration of selecting source. To change the source, click **Change Source** in the source pane or in the **Actions** group on the ribbon. Then repeat the steps described above.
 - e. Select the node that stores data you wish to migrate. If working in a large environment, enter the name of the node (for example, place and room) into the **Input Keyword** text box to search for the desired node. You can only search for the nodes that have names displayed in the currently expanded tree. The nodes that are not displayed in the expanded tree cannot be searched.
 - f. Select the source node by selecting the corresponding checkbox.
- 2. In the **Destination** pane, click the farm name or **My Registered Sites** to expand the data tree

***Note**: Make sure that you have configured the migration database; otherwise, the destination tree will be unavailable. For details on configuring a migration database, refer to <u>Configuring Migration Databases</u>.

To select the destination node:

- a. Find the destination node that you wish to migrate the source data to.
- b. To narrow down the search criteria and display fewer nodes on the tree, rightclick the specified node and select **Advanced Search**. In the **Advanced Search** interface, click **Add a Criterion** and configure the following settings:
 - i. **Rule** Select the rule for this search. The table below lists the supported rules for each node that is supported for Advanced Search.

Environment	Node	Rule
SharePoint On- Premises	Farm Level	Web Application: URL
	Web Application Level	Site Collection: Name
		Site Collection: URL
	Sites	Site: Name
		Site: URL
	Lists	List/Library: Name
		List/Library: URL
SharePoint Online	Sites	Site: Name
(My Registered Sites)		Site: URL
	Lists	List/Library: Name
		List/Library: URL

- ii. **Condition** Select the condition for the rule from the drop-down list.
- iii. **Value** Enter the value for the rule in the text box.

To add more criteria, click **Add a Criterion**, and repeat steps above. You can change the logical relationships between the criteria by clicking the **And** or **Or**. By default, the logical relationship is set to **And**. **And** means that the child nodes that meet all of the criteria will be included in the result. **Or** means that the child nodes that meet any criterion will be included in the result. The **Basic Filter Condition** area displays the logic relationships of filter criteria.

Click **Search** to start searching the child nodes.

- Select the destination node by clicking corresponding radio button. You can also create a new site collection or site by entering the specified name and click
 Create Container. For details on creating containers, refer to Creating Containers.
- 3. There are two methods to saving and/or running this job:

- Click Run Now to perform a migration job immediately, and then the Run Now window appears. For more information on how to configure the Run Now window, refer to Configuring the Run Now Interface.
- Click Save As New Plan, and then you are brought to the Save As New Plan
 interface. For more information on how to configure the Save As New Plan
 interface, refer to Configuring the Save As New Plan Interface.

Creating Containers

Containers are created in the destination prior to a migration in order to store the migrated content. The destination container in Quickr Migration can be a Web application, site collection, or site.

DocAve allows you to create containers in SharePoint without leaving the DocAve interface, allowing you to perform migration tasks without having to use SharePoint to create all of the necessary containers in the destination.

To create a container, in the Destination pane, enter the name of a new container in the available field, and then click **Create Container**. The **Create Container** interface will pop up. Depending on the container type you are creating, configure the settings for each type of container as such:

Creating a Site Collection

Configure these settings in the **Create Container** window:

- **Title and Description** Enter the **Title** of the new site collection and a **Description** for future references.
- **Template Selection** Select the desired language from the **Select a language** drop-down list. Then select a site template for this new site collection. Click on a tab to access the templates listed in that category, or click on the **Custom** tab and select **Select Template Later...** to not choose a template upon creation.
- **Primary Site Collection Administrator** Enter the **Username** of the primary administrator for this site collection. Then click the check (button to check whether the user is valid, or click the browse (button to select people and groups in a new page.
- **Secondary Site Collection Administrator** Enter the **Username** of the secondary administrator for this site collection.
- **Quota Template** Select the storage quota template to apply to this site collection.
- **Content Database** Select the Content Database for this site collection

Click **OK** to create the new site collection, or click **Cancel** to close the **Create Container** window.

Creating a Site

Configure these settings in the **Create Container** window:

- **Title and Description** Enter the **Title** of the new site and a **Description** for future references.
- **Template Selection** Select the desired language from the **Select a language** drop-down list. Then select a site template for this new site. Click on a tab to access the templates listed in that category.
- **Permissions** Select **Use unique permissions** to allow a unique set of users access to this new site. Select **Use same permissions as parent site** to allow the same users who can access the parent site access to this new site.
- **Navigation** Select the **Yes** radio button if you want a link to this site to appear in the Quick Launch and top link bar of the parent site.
- **Navigation Inheritance** Select **Yes** to use the top link bar from the parent site.

Click **OK** to create the new site, or click **Cancel** to close the **Create Container** window.

Configuring the Run Now Interface

In the **Run Now** interface, configure the following settings to perform a migration immediately:

- Conflict Resolution Specify the conflict resolution when the item name in the Quickr conflicts with an existing item in the SharePoint. For the Container Level, the conflict resolutions provided are Merge and Skip. Merge requires you to check the lower objects, and configure the Content Level conflict resolution. Skip provides the configuration of the content level conflict resolution optional. For details about conflict resolution, refer to Appendix D: Conflict Resolution.
- 2. **Profile Selection** Configure the related migration options, filter options, mapping options and advanced options for the migration job. Select a profile from the drop-down list. Quickr Migration provides you a default main profile named **Default Profile**.
- 3. **Migration Action** Choose one of the following migration action:
 - **Attach** A site for the source place will be created underneath the selected destination node, and a site for the source room will be created underneath the site for the place.
 - **Merge** The content of the source place will be added to the selected destination node, and a site for the source room will be created underneath the destination node.
- 4. **Destination Agent Group** Select a destination agent group to execute the migration job. An agent group can contain multiple agents for load balancing and better performance.

- *Note: This section only appears when the destination node is in SharePoint onpremises.
- 5. **Migration Database** Use the migration database to store links within the source data. You can also choose one of the following options:
 - Store job data in the migration database Select this checkbox to store detailed job information in the following tables within the migration database:
 DocAve6.QuickrM.JobDetail, DocAve6.QuickrM.JobNotification, and DocAve6.QuickrM.JobStatistics. For more information about the tables, refer to Appendix A: Quickr Migration Database Information.
 - **Store log information in the migration database** Select this checkbox to store log information in the **DocAve6.QuickrM.JobLogs** table within the migration database. For more information about the table, refer to <u>Appendix A:</u> Quickr Migration Database Information.

Check whether the migration database that you previously configured is available by clicking **Test**. After the testing is completed, click **Details**, Agent Name and Status are displayed.

- 6. **Notification** Select the e-mail notification profile for sending the notification report. For more information on working with notification policies, refer to the <u>DocAve 6 Control Panel Reference Guide</u>.
- 7. Job Status Option Choose whether to take the metadata/security exceptions into consideration for the Quickr migration job status. If the content metadata or security fails to migrate and you select the Ignore metadata/security exceptions checkbox, the migration job status will be Finished. Otherwise, the job status will be Finished with Exceptions.
- 8. Click **OK** to run the job immediately or click **Cancel** to return to the **Home** page of Online Migration.

Configuring the Save As New Plan Interface

In the **Save As New Plan** interface, configure the following settings to build up a migration plan:

- 1. **Plan Name** Enter a name for the plan that you are about to create. Then enter an optional **Description**.
- 2. **Profile Selection** Configure the related migration options, mapping options and advanced options for the migration job. Select a profile from the drop-down list to apply the migration settings to the migration job. Quickr Migration provides you a default main profile named **Default Profile**.
- 3. **Migration Action** Choose one of the following migration action:

- **Attach** A site for the source place will be created underneath the selected destination node, and a site for the source room will be created underneath the site for the place.
- Merge The content of the source place will be added to the selected destination node, and a site for the source room will be created underneath the destination node.
- 4. **Destination Agent Group** Select a destination agent group to execute the migration job. An agent group can contain multiple agents for load balancing and better performance.
 - ***Note**: This section only appears when the destination node is in SharePoint on-premises.
- 5. **Schedule Selection** Select one type of schedule to run the plan.
 - **No schedule** Select this option to run the plan manually.
 - Configure the schedule myself Select this option and the Schedule Settings section appears under Schedule Selection.
 - *Note: If any of the Domino Admin, Lotus Notes, Domino Designer, and Migrator Tool is being used while the job is running, the job may fail. Make sure none of them is being used while the job is running.
- 6. Schedule Settings (This section only appears when you choose Configure the schedule myself) Click Add Schedule to create a new schedule. For details about configuring a schedule, refer to Configuring the Add Schedule Interface. To preview a configured schedule, select the schedule and click Calendar View to view it in a calendar. You can delete a schedule by clicking the delete (✗) button behind a corresponding schedule.
- 7. **Notification** Select the e-mail notification profile for sending the notification report. For more information on working with notification policies, refer to the <u>DocAve 6 Control Panel Reference Guide</u> when a certain triggering event occurs.
- 8. **Associated Plan Group** Select an associated plan groups or create a new plan group in the **Associated plan group(s)** drop-down list in order to make the plan run according to the selected plan group settings. For more information on plan groups, refer to the DocAve 6 Control Panel Reference Guide.
- 9. **Migration Database** Use the migration database to store link data. You can also choose one of the following options:
 - Store job data in the migration database Select this checkbox to store detailed job information in the following tables within the migration database:
 DocAve6.QuickrM.JobDetail, DocAve6.QuickrM.JobNotification, and DocAve6.QuickrM.JobStatistics. For more information about the tables, refer to Appendix A: Quickr Migration Database Information.

• **Store log information in the migration database** – Select this checkbox to store log information in the **DocAve6.QuickrM.JobLogs** table within the migration database. For more information about the table, refer to <u>Appendix A:</u> <u>Quickr Migration Database Information</u>.

Check whether the migration database that you previously configured is available by clicking **Test**. After the testing is completed, click **Details**, Agent Name and Status are displayed.

- 10. When finished configuring the plan, select one of the following options:
 - Click **Save** to save the plan you have configured. The **Plan Manager** interface appears. For more information, refer to <u>Managing Plans</u>.
 - Click the triangle next to Save, then select Save and Run Now to save the plan and execute it right away. Then the Run Now window appears. Configure the following settings:
 - o **Options** Select a type of migration for this migration job.
 - **Full migration** Choose this option to migrate all contents from the source node to the destination node according to the profile.
 - Incremental migration Choose this option to only migrate the source node content that has been modified (Add and Modify) since the last migration job and the content that failed to be migrated in the last migration job.
 - Conflict Resolution Specify the conflict resolution when the item name in Quickr conflicts with an existing item in SharePoint. For Container Level, the conflict resolutions provided are Merge and Skip. Merge requires you to check lower objects, and configure the Content Level conflict resolution. Skip provides the configuration of Content Level conflict resolution optional. If you select Incremental migration in Options and do not select Skip as Content level conflict resolution, you can also choose whether to Remigrate the objects whose metadata/securities failed to be migrated in the last migration job. For details about conflict resolution, refer to Appendix D: Conflict Resolution.
 - Job Status Option Choose whether to take the metadata/security exceptions into consideration for the Quickr migration job status. If the content metadata or security fails to migrate and you select the Ignore metadata/security exceptions checkbox, the migration job status will be Finished. Otherwise, the job status will be Finished with Exceptions.
- 11. Click **OK** to run the online migration job.

Configuring the Add Schedule Interface

In the **Add Schedule** interface, configure the following settings to add a schedule:

- Options Select a type of migration for the customized schedule. Choose Full
 migration to migrate all contents from the source node to the destination node
 according to the profile. Choose Incremental migration to only migrate the modified
 content (Add and Modify) and the failed content of the source node since the last
 migration job.
- 2. Conflict Resolution Allows you to specify the conflict resolution for handling when the item name in Quickr conflicts with an existing item in SharePoint. For the Container Level, the conflict resolutions provided are Merge and Skip. Merge requires you to check lower objects for conflicts, and configure content level conflict resolution. Skip provides the configuration of the Content Level resolution optional. If you select Incremental migration in Options and do not select Skip as Content level conflict resolution, you can also choose whether to Remigrate the objects whose metadata/securities failed to be migrated in the last migration job. For details about conflict resolution, refer to Appendix D: Conflict Resolution.
- 3. **Schedule Settings** Specify the frequency to run the recurring schedule. Enter an integer into the text box and select **Minute(s)**, **Hour(s)**, **Day(s)**, **Week(s)** or **Month(s)** from the drop-down list.
- 4. **Range of Recurrence** Specify when to start and end the running recurring schedule.
 - **Start time** Set up the time to start the plan and Time Zone can be changed under the Start time.
 - *Note: The start time cannot be earlier than the current time.
 - **No end date** Select this option to repeat running the plan until being stopped manually.
 - **End after specified occurrence(s)** Select this option to stop the plan after specified occurrence(s) that you configure in the text box.
 - **End by** Set up the time to end the recurrence of plans.
- 5. Job Status Option Choose whether to take the metadata/security exceptions into consideration for the Lotus Notes migration job status. If the content metadata or security fails to be migrated and you have selected the Ignore metadata/security exceptions checkbox, the migration job status will be Finished. Otherwise, the job status will be Finished with Exceptions.
- 6. Click **Save** to save the configuration of schedule, or click **Cancel** to return to the **Save As New Plan** interface without saving any changes.

Quickr Migration for SharePoint Online

You can use Quickr Migration to migrate Quickr objects to SharePoint Online. To perform this function properly, you must register SharePoint Online site collections/OneDrive for Business/Office 365 group team sites in Control Panel. For more details, refer to the **Object Registration** section in the <u>DocAve 6 Control Panel Reference Guide</u>.

Before using Quickr Migration for SharePoint Online, make sure you have purchased the corresponding Quickr to SharePoint Online Migration licenses. You can navigate to **DocAve 6 Manager** > **Control Panel** > **License Manager**, then click **Migration** tab to view whether or not the corresponding **Quickr Migration for SharePoint Online** licenses are available.

For details on how to manage migration profiles or perform a Quickr Online Migration job, refer to <u>About Online Migrations</u>.

***Note**: Quickr Migration to SharePoint Online does not support the Create Container function at the site collection level in a SharePoint Online destination node.

*Note: In User Mapping, the Add a placeholder account to keep metadata even if the user no longer exists option is not supported for use with Quickr Migration to SharePoint Online. This option replaces non-existent destination users with a placeholder account in the destination Active Directory.

*Note: You can use a DocAve Agent that cannot connect to the internet to run a Quickr Migration job using SharePoint Online nodes. To do so, you must configure the **Agent Proxy Settings** in **Control Panel**. For more information, refer to the <u>DocAve 6 Control Panel Reference</u> Guide.

Supported and Unsupported Elements in Quickr Migrator

The following table lists the current supported and unsupported elements for Quickr Migrator.

DocAve Quickr Migrator does not support the elements that are not listed in the table below.

Source Element	Destination Object	Support Status	Note
Place	Site Collection	Supported	
	OneDrive for Business		
	Office 365 Group Team Site		
	Site		
Room	Site	Supported	
List	N/A	Unsupported	
(Quickr 8.5)			
Folder	Custom List	Supported	
	Document Library		
	Wiki Page Library		
	Discussion Board		Discussion Board is only supported when the language of the destination site collection is English.
	Folder		
Blog Place	Site Collection	Supported	
	OneDrive for Business		

Source Element	Destination Object	Support Status	Note
	Office 365 Group Team Site		
	Site		
Blog Entry	Item	Supported	
Wiki Place	Site Collection	Supported	
	OneDrive for Business		
	Office 365 Group Team Site		
	Site		
Wiki Page	Item	Supported	
Page	Item	Supported	
Draft Page	Item	Supported	
Workflow	N/A	Unsupported	
Page Revision	Item	Supported	
Page Version	N/A	Unsupported	
(Quickr 8.5)			
Calendar	Item in Calendar	Supported	
Task	Item in Task	Supported	
Bullet\Numbered List	N/A	Supported	
Table	N/A	Supported	
Image	N/A	Partially Supported	For the image that is uploaded through the External Image method,

Source Element	Destination Object	Support Status	Note
			the content of the image is not displayed in the destination.
Emoticon	N/A	Supported	
Attachment	N/A	Supported	
Hyperlink	N/A	Supported	
Customize Forms	Content Type	Partially Supported	The Sample Form is supported.
			The page that uses the Microsoft Office Custom Form can be migrated to the destination, but some redundant files are also migrated to the destination. The page uses the Imported HTML Custom Form can be migrated to the destination, but files within the page cannot be migrated to the destination.
Field-Plain Text/Rich Text/Legacy Rich Text	Column	Supported	
Field-Text Area	Column	Supported	
Field-Pop-up List	Column	Partially Supported	Only the option selected in the source is supported. The deselected options are

Source Element	Destination Object	Support Status	Note
			unsupported for migration.
Field- Date/Time/Name Pop-up	Column	Supported	
Field-Calendar Date-Time	Column	Supported	
Field-Task	Column	Supported	
Field-Notification Indicator	N/A	Unsupported	
Field-Non-Editable Rich Text	N/A	Unsupported	
Field-Content Author	N/A	Unsupported	
Field-Creation Date	N/A	Unsupported	
Field-Last Content Editor	N/A	Unsupported	
Field-Last Modified Date	N/A	Unsupported	
Field-Content Size	N/A	Unsupported	
Field-Serial Number	N/A	Unsupported	

Managing Plans

The Plan Manager allows users to view, edit, delete, test run, and run plans. After launching the migration module, click the **Plan Manager** tab next to the **Home** tab. In the **Plan Manager** interface, all plans that you have created are displayed in the main display pane.

In this interface, you can change the number of plans displayed per page. To change the number of plans displayed per page, select the desired number from the **Show rows** dropdown menu in the lower right-hand corner. To sort the plans, click the column heading such as **Plan Name**, and **Plan ID**.

Perform the following actions in the **Plan Manager** interface:

- Select a plan and click **View Details**. The source node and the destination node are displayed on the data tree. You can also click **Settings** on the ribbon to view the migration settings of this plan. When you want to change the nodes you selected or want to modify the migration settings, click **Edit** on the ribbon.
- Select a plan and click **Edit** on the ribbon to change the configurations for the selected plan. You can change the nodes you selected and modify the migration settings. Besides, you can click **Profile Settings** or **Create Container** to performing the corresponding actions.
- Select the plans that you want to delete and click **Delete** on the ribbon. A
 confirmation window appears, confirming that you want to proceed with the
 deletion. Click **OK** to delete the selected plans, or click **Cancel** to return to the
 Plan Manager interface without deleting the selected plans.
- Click **Test Run** to perform a test run job that simulates the real migration job. By
 viewing the job report of the test run, you can find whether the source contents
 can be migrated to the destination successfully, and then adjust the plans or
 optimize the settings.
 - *Note: Test Run results may differ from the results of an actual migration. Investigate Test Runs that display **Finished with Exceptions** results by reviewing the log file. If no obvious content, metadata, or permission errors are found, it is likely that the actual migration will complete successfully.
- Click **Run Now** to perform the migration job.

Quickr Migrator Tool

Quickr Migrator Tool resides in ...\AvePoint\DocAve6\Agent\bin\MigratorTool.exe. This tool is used to scan the source objects and generate the Scan Analysis Report to help determine whether there will be any potential risks in the migration job. You can also use this tool to generate the content type and user mappings for the selected places, which will be used to migrate the source content and security. Refer to the DocAve 6 Supplementary Tools User Guide for instructions on using this tool.

Appendix A: Quickr Migration Database Information

Refer to the following tables for the detailed job information stored in the migration database. In <u>Job Detail</u>, you can view the details of each migrated source object, the source/destination object ID, the URL of the source/destination object, the size of the source object, the owner of the source/destination object, the migration start time, the end time, and so on. In <u>Job Notification</u>, you can view the status of the migration job and view the comment related to the migration job. In <u>Job Statistic</u>, you can view the statistical information of the migration job, such as, the job ID, the plan ID, the source/destination start time, the source/destination end time, the source/destination Agent name, the number of migrated/failed/skipped items/folders/lists, and so on. In <u>Job Logs</u>, you can view the ID of the job that the log belongs to, the time that the log was written, the detailed log information, and the log level.

Job Detail

View the information of the job details in the table below.

Column Name	Description	Value
JobId	It is the ID of the job.	The prefix of the job ID facilitates the distinction of different migrations. The job ID prefix for Quickr migration is QM. For example, QM20120702184324729287, it indicates a Quickr migration job ID.
Sequenceld	It is the sequence ID of each migrated source object.	The value represents the sequence of each migrated source object. For example, 1, it indicates that this source object is the first migrated object.
SourceObjectId	It is the ID of the source object.	The value is the ID of the source object.
SourceObjectParentID		The value is the ID of the parent of the source object.

Column Name	Description	Value
TargetObjectId	It is the ID of the target object.	The value is the GUID of each target object level from site collection level to item level. For example, 08e90aee-c8d8-474b-8979-c1250a32b94d is the GUID of the target list. For Web application level, the value displayed is 00000000-0000-0000-0000-0000-0000-00
TargetObjectParentID		The value is blank.
SourceFullUrl	It is the full URL of the source object.	The value is the full URL of the source object. Use the value to find the source object.
TargetFullURL	It is the full URL of the target object.	The value is the full URL of the target object. Use the full URL to find the target object. If the source object is not migrated to the target, the column value is blank.
SourceObjectTitle	It is the title of the source object.	The value is the title of the source object.
TargetObjectTitle	It is the title of the target object.	The value is the title of the target object.
SourceObjectType	It is the type of the source object.	The value represents the type of the source object, which is different according to the source you selected. • 999 – Quickr Place • 998 – Quickr Room • 997 – Quickr Page • 996 – Quickr Attachment

Column Name	Description	Value
		• 995 – Quickr Folder
		• 1001 – Quickr Group
		• 1002 – Quickr User
TargetObjectType	It is the type of the target object.	The value represents the type of the target object.
		• 10001 – Web Application
		• 10002 – Site Collection
		• 10003 – Site
		• 10004 – Library
		• 10005 – List
		• 10006 – Folder
		• 10007 – Document
		• 10008 – Item
		• 10009 – Attachment
SourceObjectSizeBytes	It is the size of the source object. The unit is byte.	The value is the real size of the source object.
TargetObjectSizeBytes	It is the size of the target object. The unit is byte.	The value is the size of the target object.
SourceObjectOwner	It is the owner of the source object.	The value represents the user who creates the source object.
TargetObjectOwner	It is the owner of the target object.	The value represents the user who creates the source object.
SourceObjectVersion	It is the version of the source object.	The value represents the version information of the source object.

Column Name	Description	Value
TargetObjectVersion	It is the version of the target object.	The value represents the version information of the target object.
Operation	It is the operation performed for each source object during migration.	The value represents the operation performed when migrating the source object to the target. • 0 – None
		 1 – Skipped 2 – New Created 3 – Overwritten 4 – Appended 5 – Filtered 7 – Merge
Status	It is the migration status of the source object.	The value represents the status of the job. • 0 – Starting • 1 – Successful • 2 – Backup Failed • 3 – Restore Failed • 4 – Filtered Out • 5 – Skipped • 6 – Exceptional
StartTime	It is the time when the backup starts.	The value represents the time when the backup starts.
EndTime	It is the time when the restore completes.	The value represents the time when the restore completes.
FilteredOutPolicy	It is the status of using filter policy.	The value represents the status of using filter policy.

Column Name	Description	Value
		• 0 – Not Used
		• 1 – Used
TruncatedPolicy	It is the truncated policy that is applied to the source object.	The value represents the truncated policy that is applied to the source object.
		None – No truncated policy.
		 Truncated – The object name is truncated.
		 Renamed – The object name is renamed.
		 MoveUp – The object is moved up to the higher level.
TruncatedOrRenamedAs	It is the new name of the object in the target.	The value is the new name of the object in the target after truncating or renaming.
CustomMetadata	It is the status of using custom metadata.	The value represents the status of using custom metadata.
		• 0 – Not Used
		• 1 – Used
		The default value is false.
MetadataMapping	It is the statues of using C-Based Object Oriented Language (C# Language) Mapping.	The value represents the status of using C-Based Object Oriented Language (C# Language) Mapping.
		• 0 – Not Used
		• 1 – Used

Column Name	Description	Value
Message	It displays the migration message of the source object.	The value is the migration message of the source object.

Job Notification

View the information of the job notifications in the table below.

Column Name	Description	Value
Sequenceld	It is the ID of the sequence for each job.	The value represents the sequence of each job. For example, 1, it indicates that this job is the first migration job.
Jobld	It is the ID of the job.	The prefix of the job ID facilitates the distinction of different migrations. The job ID prefix for Quickr migration is QM. For example, QM20120702184324729287, it indicates a Quickr migration job ID.
Status	It is the status of the job.	The value represents the status of the job. • 0 – In Progress • 2 – Finished • 3 – Failed • 4 – Stopped • 7 – Finished With Exception • 8 – Paused

Column Name	Description	Value
Message	It displays the job comment.	The value displayed is the same as the comment in Statistics of Job Details.

Job Statistic

View the information of the job statistics in the table below.

Column Name	Description	Value
Jobld	It is the ID of the job.	The prefix of the job ID facilitates the distinction of different migrations. The job ID prefix for Quickr Migration is QM. For example, QM20120702184324729287, it indicates a Quickr migration job ID.
PlanId	It is the ID of the plan.	The value is the plan ID, for example, PLAN20120702184321934938.
PlanName	It is the name of the plan.	The value is the plan name. If you run a job without saving it as a plan, the value is Instance Plan.
PlanGroupId	It is the ID of the plan group.	The value is the ID of the plan group that you set for the plan.
PlanGroupName	It is the name of the plan group.	The value is the name of the plan group that you set for the plan.

Column Name	Description	Value	
SourceAgentType	It is the source Agent type.	The value represents the source Agent type. The value for Quickr is 10.	
TargetAgentType	It is the target Agent type.	The value represents the target Agent type.	
		• 5 – SharePoint 2010	
		• 6 – SharePoint 2013	
		• 12 – SharePoint 2016	
		• 11 – SharePoint Online	
SourceAgentName	It is the source Agent name.	The value is the source Agent name.	
TargetAgentName	It is the target Agent name.	The value is the target Agent name.	
Status	It is the status of the job.	The value represents the status of the job.	
		• 0 – In Progress	
		• 2 – Finished	
		• 3 – Failed	
		• 4 – Stopped	
		• 7 – Finished With Exception	
		• 8 – Paused	
Run Type	It is the type of the job.	The value represents the type of the job.	
		• 0 – Run/Rerun	
		• 1 – Test Run	

Column Name	Description	Value	
SourceStartTime	It is the time when the backup starts.	The value represents the time when the backup starts.	
SourceFinishTime	It is the time when the backup completes.	The value represents the time when the backup completes.	
TargetStartTime	It is the time when the restore starts.	The value represents the time when the restore starts.	
TargetFinishTime	It is the time when the restore completes.	The value represents the time when the restore completes.	
Description	It is the description of the job.	The value is the description of the job.	
UserName	It is the DocAve user who runs the job.	The value is the username who runs the job.	
JobOption	It is the option of the job.	The value is 0.	
JobType	It is the type of the job.	The value represents the type of the job.	
		• 0 – Full Migration	
		• 1 – Incremental Migration	
ContainerConflictResolution	It is the container conflict resolution.	The value represents the resolution of container conflict.	
		• 0 – Skip	
		• 5 – Merge	
ContentConflictResoltuion	It is the content conflict resolution.	The value represents the resolution of content conflict.	
		• 0 – Skip	
		• 2 – Append	

Column Name Description		Value	
		• 3 – Overwrite	
MigratedBytes	It is the size of the migrated data. The unit is byte.		
FailedBytes	It is the size of the data that are failed to be migrated. The unit is byte.		
SkipedBytes	It is the size of the skipped data. The unit is byte.		
FilteredBytes	It is the size of the data that is filtered out. The unit is byte.		
MigratedSiteCollectionCount	It is the number of migrated site collections.		
MigratedSiteCount	It is the number of the migrated sites.		
MigratedListCount	It is the number of the migrated lists.		
MigratedFolderCount	It is the number of migrated folders.		
MigratedItemCount	It is the number of migrated items.		
FailedSiteCollectionCount	It is the number of site collections that are failed to be migrated.		
FailedSiteCount	It is the number of the sites that are failed to be migrated.		

Column Name	Description	Value
FailedListCount	It is the number of the lists that are failed to be migrated.	
FailedFolderCount	It is the number of the folders that are failed to be migrated.	
FailedItemCount	It is the number of the items that are failed to be migrated.	
SkippedSiteCollectionCount	It is the number of the skipped site collections.	
SkippedSiteCount	It is the number of the skipped sites.	
SkippedListCount	It is the number of the skipped lists.	
SkippedFolderCount	It is the number of the skipped folders.	
SkippedItemCount	It is the number of the skipped items.	
FilteredOutSiteCollectionCount	It is the number of site collections that are filtered out.	
FilteredOutSiteCount	It is the number of sites that are filtered out.	
FilteredOutListCount	It is the number of lists that are filtered out.	
FilteredOutFolderCount	It is the number of folders that are filtered out.	

Column Name	Description	Value
FilteredOutItemCount	It is the number of items that are filtered out.	
ExceptionSiteCollectionCount	It is the number of site collections that are migrated with exception.	
ExceptionSiteCount	It is the number of sites that are migrated with exception.	
ExceptionListCount	It is the number of lists that are migrated with exception.	
ExceptionFolderCount	It is the number of folders that are migrated with exception.	
ExceptionItemCount	It is the number of items that are migrated with exception.	

Job Logs

View the information of the job logs in the table below.


Column Name	Description	Value
JobId	It is the ID of the job that the log belongs to.	The prefix of the job ID facilitates the distinction of different migrations. The job ID prefix for Quickr migration is QM. For example, QM20150210145847665555, it indicates a Quickr migration job ID.
Time	It is the time when the log is written to the table.	The value represents the time when the log was written to the table.
Message	It displays the detailed information of the log.	The value is the detailed log information. For each piece of log, there is a mark Source or Destination . Source—The log is of the actions of the source DocAve Agent. Destination—The log is of the actions of the destination DocAve Agent.
LogLevel	It is the level of the log.	The value represents the level of the log.
		INFO – Information

Column Name	Description	Value	
		•	WARN – Warning
		•	ERROR – Error
		•	DEBUG – Debug


Appendix B: Quickr Migrator Customization Support Table


The following table shows what kinds of source node are supported to be migrated to the corresponding destination nodes


 $\sqrt{}$ means the migration is supported.





DocAve® 6 Quickr Migrator











Appendix C: Quickr Migrator Configuration File

You are allowed to manage Quickr Migration functions by configuring the attribute of the corresponding node in the **QuickrMigrationWorker.xml** configuration file. Navigate to to ...\AvePoint\DocAve6\Agent\data\Migrator\QuickrSettings\ConfigurationFile on the machine where the source DocAve Agent is installed and find the **QuickrMigrationWorker.xml** file.

QuickrMigrationWorker.xml

Open the **QuickrMigrationWorker.xml** file with Notepad. Refer to the information below to configure the attribute in the **QuickrMigrationWorker.xml** file.

- UsingSessionAddressBook This node allows you to choose the method to retrieve the Domino Server.
 - True True means Quickr Migrator retrieves the Domino Server from Address Book.
 - False False means Quickr Migrator retrieves the Domino Server from the attributes of DominoServer and DirectoryDatabasePath. If no attribute is defined for DominoServer or DirectoryDatabasePath, Quickr Migrator retrieves the Domino Server from names.nsf database of the local Domino Server.
- DominoServer The Domino Server name.
- **DirectoryDatabasePath** The relative path of the Domino Server's **names.nsf** database. If the names.nsf database resides in ...\notes\data, enter **names.nsf**. If the names.nsf database resides in ...\notes\data\test, enter **test\names.nsf**.
- **ServerItem** Enter the name of the Domino Server that will be loaded when selecting the source, or the IP address of the server where the Domino Server resides.
- **QuickrFormColumn** This node allows you to define the name of the field from which the form name is retrieved.
- **ShowResponseTo** This node allows you to choose whether to migrate the Response To field.
 - False False means the Response To field will not be migrated to the destination in the migration job
 - True True means the Response To field will be migrated to the destination in the migration job.
- **IsCheckVersion** This node allows you to choose whether to check the version of Quickr when configuring a Quickr connection.

- False False means the version of Quickr will not be checked when configuring a Quickr connection.
- True True means the version of Quickr will be checked when configuring a Quickr connection.
- **PerformanceLogDisable** This node allows you to choose whether to collect the performance log.
 - False False means the performance log will be collected when performing Quickr migration jobs. The performance log file will be generated in the folder that is named by Job ID and the folder is within...\AvePoint\DocAve6\Agent\jobs.
 - True True means the performance log will not be collected when performing Quickr migration jobs.
- **UpdateContentType** This node allows you to choose whether to allow SharePoint existing content types to be updated if an existing content type is specified in Content Type Mapping.
 - False False means the existing SharePoint content type will not be updated.
 - True True means the existing SharePoint content type will be updated and the Quickr form will be mapped to the content type.
- **MigrateFormToSiteContentType** This node allows you to choose whether to migrate the source form to SharePoint site content type.
 - False False means the source form will not be migrated to the site content type but will be migrated to the list content type.
 - True True means the source form will be migrated to the site content type.

*Note: When you choose SharePoint Online as the destination environment, the source form will be migrated to the site content type regardless if the value of MigrateFormToSiteContentType is False or True.

• **CreateNewContentType** – This node allows you to choose whether to create a new site content type for the source form when the site content type name already exists in the destination.

*Note: This only takes effect when the value of MigrateFormToSiteContentType is True or the destination environment is SharePoint Online.

 False – False means no new site content type will be created for the source form. The existing site content type will be updated and the fields of the source form will be added to the existing site content type.

- True True means a new site content type will be created for the source form. The new site content type is named by adding a suffix (_1, _2, ..., increasing in numerical value), for example, content type_1.
- ManagedMetadataConfig CreateNewTermIfDoesNotExist This node allows you to choose whether to create new terms in the destination when the source field values do not exist in the destination.
 - o **True** True means Quickr Migration will create new terms in the destination when the source field values do not exist in the destination.
 - o **False** False means Quickr Migration will not create new terms in the destination when the source field values do not exist in the destination.

Appendix D: Conflict Resolution

In this appendix, the detailed information of each resolution is described. View the tables below for your reference.

Container Level Conflict Resolution

Resolution	Object	Conflict	No Conflict
Skip	Configuration	Ignore the conflicting configuration and do nothing on the destination.	A new SharePoint object will be created.
	Security	Ignore the conflicting security and do nothing on the destination.	A new SharePoint object will be created.
Merge	Configuration	Merge the settings in the destination node with settings from the source node.	A new SharePoint object will be created.
	Security	Permissions – Source permissions that do not already exist in the destination node will be added to the destination node.	A new SharePoint object will be created.
		Permission Levels – the permission levels that do not already exist in the destination node will be added to the	
		destination node. The permission levels that already exist in the	

Resolution	Object	Conflict	No Conflict
		destination node will not be replaced.	

Content Level Conflict Resolution

Resolution	Object	Conflict	No Conflict
Overwrite	Content	Delete the conflicting content on destination first and overwrite it with the source content.	A new SharePoint object will be created.
Skip	Content	Ignore the conflicting content and do nothing on destination.	A new SharePoint object will be created.
Append	Content	The conflicting content will not be deleted; and the conflicting data will be transferred to the destination by adding a suffix (_1, _2 increasing in numerical value).	A new SharePoint object will be created.

Notices and Copyright Information

Notice

The materials contained in this publication are owned or provided by AvePoint, Inc. and are the property of AvePoint or its licensors, and are protected by copyright, trademark and other intellectual property laws. No trademark or copyright notice in this publication may be removed or altered in any way.

Copyright

Copyright ©2012-2018 AvePoint, Inc. All rights reserved. All materials contained in this publication are protected by United States and international copyright laws and no part of this publication may be reproduced, modified, displayed, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the prior written consent of AvePoint, 525 Washington Blvd, Suite 1400, Jersey City, NJ 07310, USA or, in the case of materials in this publication owned by third parties, without such third party's consent. Notwithstanding the foregoing, to the extent any AvePoint material in this publication is reproduced or modified in any way (including derivative works and transformative works), by you or on your behalf, then such reproduced or modified materials shall be automatically assigned to AvePoint without any further act and you agree on behalf of yourself and your successors, assigns, heirs, beneficiaries, and executors, to promptly do all things and sign all documents to confirm the transfer of such reproduced or modified materials to AvePoint.

Trademarks

AvePoint®, DocAve®, the AvePoint logo, and the AvePoint Pyramid logo are registered trademarks of AvePoint, Inc. with the United States Patent and Trademark Office. These registered trademarks, along with all other trademarks of AvePoint used in this publication are the exclusive property of AvePoint and may not be used without prior written consent.

Microsoft, MS-DOS, Internet Explorer, Office, Office 365, SharePoint, Windows PowerShell, SQL Server, Outlook, Windows Server, Active Directory, and Dynamics CRM 2013 are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

Adobe Acrobat and Acrobat Reader are trademarks of Adobe Systems, Inc.

All other trademarks contained in this publication are the property of their respective owners and may not be used without such party's consent.

Changes

The material in this publication is for information purposes only and is subject to change without notice. While reasonable efforts have been made in the preparation of this publication to ensure its accuracy, AvePoint makes no representation or warranty, expressed or implied, as to its completeness, accuracy, or suitability, and assumes no liability resulting from errors or omissions in this publication or from the use of the information contained herein. AvePoint reserves the right to make changes in the Graphical User Interface of the AvePoint software without reservation and without notification to its users.

AvePoint, Inc. 525 Washington Blvd Suite 1400 Jersey City, NJ 07310 USA